

Exam : EMC E20-340

**Title : Clariion Solutions
Implementation**

Version : Demo

Important Note, Please Read Carefully

Other TestInside products

[All TestInside.com IT Exam Products](#)

Our products of Offline Testing Engine

Use the offline Testing engine product to practice the questions in an exam environment.

Build a foundation of knowledge which will be useful also after passing the exam.

[TestInside Testing Engine](#)

Latest Version

We are constantly reviewing our products. New material is added and old material is revised. Free updates are available for 90 days after the purchase. You should check your member zone at TestInside and update 3-4 days before the scheduled exam date.

Here is the procedure to get the latest version:

1. Go to <http://www.TestInside.com>
2. Log in the **Member Center**
3. The latest versions of all purchased products are downloadable from here. Just click the links.

Feedback

If you spot a possible improvement then please let us know. We always interested in improving product quality.

Feedback should be send to sales(at)TestInside.com. You should include the following: Exam number, version, page number, question number, and your login Account.

Our experts will answer your mail promptly.

Explanations

This product does not include explanations at the moment. If you are interested in providing explanations for this exam, please contact sales(at)TestInside.com.

1. What is the maximum number of drives and LUNs supported by a CX3-40?

- A. 240 drives and up to 1,024 LUNs
- B. 256 drives and up to 1,024 LUNs
- C. 480 drives and up to 2,048 LUNs
- D. 512 drives and up to 4,096 LUNs

Answer: A

2. Which port is required at installation in order to configure a back-end bus on a CX4?

- A. Port 0 A-Bus 0
- B. Port 1 B-Bus 1
- C. Port 0 A-Bus1
- D. Port 3 B-Bus2

Answer: A

3. After the initial CX4 configuration has been set up and persisted, a customer would like to add additional back-end and front-end ports. In the diagram, which logical port assignments will be given to port 1 and port 3, respectively?

- A. Port 1 - BE1, Port 3 - FE3
- B. Port 1 - BE2, Port 3 - FE2
- C. Port 1 - FE1, Port 3 - BE2
- D. Port 1 - FE3, Port 3 - BE2

Answer: A

4. What is the hard-coded Ethernet IP address for a SP B service port in a CX3-20 and CX3-40?

- A. 128.221.1.251
- B. 128.122.2.251
- C. 128.221.1.250
- D. 128.122.2.250

Answer: A

5. Using the Fibre Channel fan-in rule, what is the maximum number of storage systems a host can attach to?

- A. 2
- B. 4
- C. 8
- D. 16

Answer: B

6. Which cable type is required to connect the DAE2P to the DAE3P?

- A. HSSDC - HSSDC
- B. HSSDC2 - HSSDC2
- C. HSSDC - HSSDC2
- D. HSSDC - HSSDC3

Answer: B

7. Which port would you use to Telnet directly into the CLARiiON?

- A. Comm Port RS-232
- B. Management LAN
- C. Service LAN
- D. SPS Serial Port RS-232

Answer: A

8. According to EMC best practice, what is the proper sequence for powering up a CLARiiON array?

- A. Power on SP A and then power on SP B
- B. Power on the master switch and then power on each SP
- C. Power on the master switch; both SPs will power on automatically
- D. Turn on the power switch for each SPS and then power on the master switch

Answer: D

9. What is the first thing you need to know when starting the Initialization Utility?

- A. Domain that the array is apart of
- B. IP address of Management Port
- C. Serial number of the array
- D. Version of FLARE on the array

Answer: C

10. What is the correct command to add user security?

- A. navisecli -AddUserSecurity -scope 0 -user -username -password mypass
- B. navisecli -AddUserSecurity -password mypass -scope 0 -user username
- C. navicli -AddUserSecurity -scope 0 -user -username -password mypass
- D. navicli -AddUserSecurity -password mypass -scope 0 -user -username

Answer: B

11. What is the correct command to delete user security?

- A. navicli -RemoveUserSecurity -scope 0 -user -username -password mypass
- B. navicli -RemoveUserSecurity -password mypass -scope 0 -user username
- C. navisecli -RemoveUserSecurity -scope 0 -user -username -password mpass
- D. navisecli -RemoveUserSecurity -password mypass -scope 0 -user -username

Answer: D

12. What is the function of IP address filtering?

- A. Restricts access to iSCSI ports, EMCRemote, and communication between SPs.
- B. Restricts access to Navisphere Service and Serial ports.
- C. Restricts access to specific management clients.
- D. Restricts access to the Loopback Address.

Answer: C

13. Which access will be restricted by using IP address filtering?

- A. CIMON debug menu
- B. CIMON debug

- C. iSCSI ports
- D. Navisphere Service

Answer: A

14. IP address filtering restricts access for Navisphere Manager, Navisphere Express, and Navisphere Secure CLI. Which access does it allow?

- A. Access to iSCSI ports, EMCRemote, and communication between SPs
- B. HAVT Reports and CIMON Debug
- C. Navisphere Management Ports and EMCRemote
- D. Navisphere Service, serial ports, and Navisphere Management Ports

Answer: A

15. How can PKCS#12 files be imported?

- A. Through GUI
- B. Through Navi CLI
- C. Through Secure CLI
- D. Through serial cable

Answer: C

16. Which Navisphere utility can be used to exchange a faulted I/O module in CX4?

- A. Initialization
- B. Initialization
- C. Replacement
- D. Initialization

Answer: C

17. Which tool is now required when upgrading FLARE or upgrading a DAE with FLARE 26?

- A. CLARiiON software installer
- B. Navisphere Manager
- C. NDU package enabler

D. NST software assistant

Answer: D

18. Which tasks do the two items (outlined in red) perform?

- A. Open a new browser window and display online help
- B. Open a new enterprise storage window and a wizard for routine tasks
- C. Open a new enterprise storage window and display online help
- D. Open EMC ControlCenter and display online help

Answer: C

19. A customer currently owns five CLARiiON systems. They can only access Navisphere when they point their web browser to the IP addresses of two of the five storage systems. What would be changed to allow them to use all of the arrays for Navisphere access?

- A. Log in to CLARiiON as Global Administrator; under the Security Menu select "Configure Manager Launch from Storage System"; move the three systems to the "Storage Systems with Manager Launch enabled" list
- B. Log in to CLARiiON as Local Administrator; under the Security Menu select "Configure Manager Launch from Storage System"; move the remaining arrays to the "Storage Systems with Manager Launch enabled" list
- C. Log in to the CLARiiON as a Global Administrator; under the Security Menu select "Configure LDAP Connection Settings"; move the remaining arrays to the "Service Connection(s)" list
- D. Log in to the CLARiiON as a Local Administrator; under the Security Menu select "Configure LDAP Connection Settings"; move the remaining arrays to the "Service Connection(s)" list

Answer: A

20. Which type of port is shown in the illustration?

- A. Fibre Switch
- B. Fibre Switch
- C. MirrorView
- D. Fibre Switch

Answer: C

Testinside

Testinside.com was founded in 2002. The safer,easier way to help you pass any IT Certification exams . We provide high quality IT Certification exams practice questions and answers(Q&A). Especially [Adobe](#), [Apple](#), [Citrix](#), [Comptia](#), [EMC](#), [HP](#), [Juniper](#), [LPI](#), [Nortel](#), [Oracle](#), [SUN](#), [Vmware](#) and so on. And help you pass any IT Certification exams at the first try.

English	<u>http://www.testinside.com</u>
Chinese (Traditional)	<u>http:// www.testinside.net</u>
Chinese (Simplified)	<u>http:// www.testinside.cn</u>